

SMS Settings

SMS Settings define how the verification/password messages sent to guests are generated and which service delivers them. If you enabled the module on the **SMS Portal Settings** page, this page must also be filled in correctly before a guest can receive a code.

“ How do I open this screen? From the left menu, go to **Settings → SMS Settings**.

USEROAM

Menü

Dashboard

Bumerang

Misafirler

Karşılama Portalı

Analiz ve Raporlar

Ayarlar

Hotspot QR Kodu

Bildirimler

Cihaz Ayarları

Yöneticiler

Yönetici Profilleri

SMS ayarları

Whatsapp Ayarları

Lisans Bilgileri

SMS ayarları

Şuan Buradasınız

Dashboard > SMS ayarları

SMS API ayarları

Özel API:

Firmanıza ait özel SMS entegrasyonu sağlayabilirsiniz. Useroam başlıklı SMS gönderilmesi için özel seçeneğinin kapatılması gerekmektedir.

Karakter Uzunluğu

-

+

Karakter Tipi

Sadece Küçük Harf

Grup

Kullanıcı kayıtlı ise yeni şifre gönder

Gönderilecek Mesaj

Kaydet

Copyright ©2025. Useroam Teknoloji

Yardım | Şartlar | Gizlilik

1. SMS API Settings

- **Custom API** (on screen: *Özel API*): turn on to use your own SMS integration. **To send messages under the Useroam sender name, this option must stay off.** In short: turn it on to send under your own brand header, leave it off to use the shared Useroam header.

Enabling the custom API reveals these fields:

- **SMS Provider:** *Mobilışim (Ekomesaj)* is a ready-made integration; choosing *Other* means you define every request parameter yourself.
- **URL:** the provider's send endpoint.
- **HTTP Method:** *GET* or *POST* — pick whichever the provider's documentation requires.
- **Use country code:** numbers are sent with the country code (e.g. 90) prefixed.
- **Add leading zero:** prefixes the number with ☐. It is not used together with the country code — pick whichever format your provider expects.
- **Response value:** the value the provider returns on a successful send. The system uses it to decide whether a message counts as delivered.
- **Username, Password, Header:** the account credentials and the SMS sender name (originator) used by the Mobilışim (Ekomesaj) integration.

Request parameters

This table, with **Parameter** and **Parameter Value** columns, is where you add the fields your provider expects. Use + to add a row and - to remove one. When the *Other* provider is selected, the request is built from this table.

“ **SMS Test:** the test dialog on the page shows the URL of the request that will be built. Use it to confirm the parameters combine correctly before contacting the provider.

2. Password (coupon) generation

- **Character Length:** how many characters the code sent to the guest has. Use the - and + buttons to adjust. A short code is easier to type; a long one is harder to guess.
- **Character Type:** *Lowercase Letters Only, Uppercase Letters Only, Letters Only, Numbers Only* or *All*. Since guests type it on a phone, *Numbers Only* is usually the most practical.
- **Group:** the user group that guests registering by SMS are added to. The group's quota, speed and duration rules apply to them. Groups are managed on the **Guests → Groups** page.
- **If the user is registered, send a new password:** when a previously registered number logs in again, a new password is generated and sent. If off, the guest continues with their existing password.
- **Message to be Sent:** the SMS text delivered to the guest. Keep the placeholder that carries the password in the text; otherwise the guest never sees the code.

Confirm your changes with **Save**.

Related pages: Captive Portal → SMS Portal Settings, Guests → Groups, Analytics and Reports → SMS / WhatsApp Reports.

Revizyon #2

tugay tarafından 11 Ağustos 2026 06:47:14 oluşturuldu

tugay tarafından 11 Ağustos 2026 08:20:58 güncellendi