


Hotspot QR Code

The Hotspot QR Poster builds the QR poster you place on tables, walls or menus so guests can join your Wi-Fi in **a single tap**. Scanning the code connects the device to the network and opens the captive portal.

“ **How do I open this screen?** From the left menu, go to **Analytics and Reports → Hotspot QR Code**.

Note: the field labels on this screen are still shown in Turkish; the on-screen text is given in brackets.



The page has two halves: the **settings** on the left and a **live poster preview** on the right. Every change appears in the preview instantly.

1. Network details

- **Wi-Fi name (SSID) (WiFi adı (SSID))**: the name of your guest network. The QR code is generated from this name — **if it is wrong, the connection will not work**.
- **Password (Şifre)**: your network password.
- **Open network (no password) (Açık ağ (şifresiz))**: tick this if your network has no password; the password field is then disabled.

2. Poster content

- **Title (business)** (*Başlık (işletme)*): your business name, shown in large type on the poster.
 - **Top line** (*Üst yazı*): the short text above the title (for example "Free Wi-Fi").
 - **Logo**: the device's portal logo is pulled in automatically; you can upload a different image if you prefer. The logo appears **in the centre of the QR code**.
 - **Poster theme: Light** (*Aydınlık*) or **Dark** (*Koyu*). Choose according to where the poster will hang — dark works better in dim spaces, light prints better.
-

3. iOS login helper

The **iOS login helper** — "**open in Safari**" **QR code** option adds a second QR code for the cases where the captive screen does not open on iPhones.

- **Login (Safari) address**: when the guest scans this code, the portal opens directly in Safari and the one-time code (OTP) works there.

Important: this address **must be HTTP** (a domain without HSTS). If you enter an HTTPS address, the iOS redirect will not work.

4. Output

- **Download poster (PNG)**: downloads the whole design as an image, ready for print or a digital screen.
- **QR only**: downloads just the QR code, for placing into your own menu or poster design.
- **Print**: sends the poster straight to the printer.

“ **Embedding Wi-Fi in QR codes**: if you want menu and hotel QR codes to connect the device automatically when scanned, enable *Embed Wi-Fi in QR codes* on the **Captive Portal → Portal Settings** page.

“ **Related pages**: **Captive Portal → Portal Settings** (SSID/password and QR embedding), **Restaurant Solution → Online Menu**.

Revizyon #3

tugay tarafından 11 Ağustos 2026 07:07:24 oluşturuldu

tugay tarafından 11 Ağustos 2026 10:33:52 güncellendi