

Sophos API Connection

Useroam uses the Sophos Firewall API to create and remove hotspot user sessions automatically. This page shows how to create the API user and grant the API permission on the Sophos side.

“ **When do I need this?** Complete these steps after the **Sophos Integration Guide**, whenever Useroam has to manage users over the API.

Creating a new profile

In Sophos, go to **Profile > Device Access** in the left menu and create a new profile. Grant all permissions.

SSD: A recommended SSD firmware update that improves SSD performance is available for this firewall. You can upgrade it through the CLI. For details, see [KB-000045830](#).

Feedback How-to guides Log viewer Help admin

Basak Filtre San. Ve Tic. Ltd Şti.

Schedule	Access time	Surfing quota	Network traffic quota	Decryption profiles	IPsec profiles	Device access
----------	-------------	---------------	-----------------------	---------------------	----------------	---------------

Edit profile

Profile name * Useroam Api

Configuration	☐ None	☐ Read-only	☒ Read-write
Control center	☐	☐	☒
Initial setup	☐	☐	☒
System	☐	☐	☒
Objects	☐	☐	☒
Network	☐	☐	☒
Identity	☐	☐	☒
Wireless protection	☐	☐	☒
Rules and policies	☐	☐	☒

Save Cancel

Creating the API user

In Sophos, go to **Authentication > Users > New user** in the left menu and create a new user. For **User Profile**, select the profile you created in the previous step.

SOPHOS FW

SSD: A recommended SSD firmware update that improves SSD performance is available for this firewall. You can upgrade it through the CLI. For details, see KB-000045830.

Authentication

Feedback How-to guides Log viewer Help admin

Basak Filtre San. Ve Tic. Ltd Şti.

Servers Services Groups **Users** Multi-factor authentication Web authentication Clientless users STAS

Edit user

Username * useroamapi

Name * useroamapi

Description Description

User type * ☐ User ☒ Administrator

Profile * Useroam Api

Password * ***** [Change Password](#)

Email * useroamapi@useroam.com Quarantine digest will be sent to the first email address only.

Internet usage time 00:00 (HH-MM)

Policies

Group * Open Group

Surfing quota *

Save Reset user accounting View usage Cancel

Granting the API permission

In Sophos, open **Backup & Firmware** from the left menu, switch to the **API** tab, add the entry below to the **API Configuration** field and click +.

SOPHOS FW

SSD: A recommended SSD firmware update that improves SSD performance is available for this firewall. You can upgrade it through the CLI. For details, see KB-000045830.

Backup & firmware

Feedback How-to guides Log viewer Help admin

Basak Filtre San. Ve Tic. Ltd Şti.

Backup & restore **API** Import export Pattern updates

API configuration

API configuration ☒ Enabled

Allowed IP address 104.247.174.120

Search / Add

Apply

API explorer

Request XML string *

Parse and apply

Tip: the API user's credentials must match the ones entered on the device record in the Useroam panel. If you change the password later, update it in the panel as well.

Revizyon #1

tugay tarafından 10 Ağustos 2026 22:55:58 oluşturuldu

tugay tarafından 10 Ağustos 2026 22:55:58 güncellendi